

Operation manual of LTSA_gui.exe


Tzu-Hao Harry Lin
schonkopf@gmail.com

Preparation of using LTSA_gui.exe

- Install MATLAB Runtime R2017a (9.2)
<https://www.mathworks.com/products/compiler/matlab-runtime.html>
- Prepare your long-duration recordings within one folder
 - It must be wav file!
 - Do not put recordings from different sites at the same folder
 - Beginning time of a recording should be stamped on the file name

Open the LTSA_gui.exe

- Double clicked the LTSA_gui.exe, a window will displayed to ask you select the recordings you want to analyze
- Go to the folder you have prepared, and then select any one recording
- The program will process all the recordings contain in the same folder
 - Not including subfolders



Open Cancel

Control panel of LTSA_gui.exe

Parameters of generating
a long-term spectrogram

Figure 1

Recording channel: 1

Recording environment: Wat

Recording sensitivity: 0

Reading interval (sec): 300

Time resolution (sec): 10

FFT size (samples): 1024

Upper frequency limit (Hz): 90000

Lower frequency limit (Hz): 100

Output file name: Input file name

1207984160.180528171502.wav

1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27

Year: 12 13

Month: 14 15

Day: 16 17

Hour: 18 19

Minute: 20 21

Second: 22 23

Extra labels before input year: 20

Run analysis View LTS

Time stamp
information

Parameters of generating a long-term spectrogram

- **Recording channel:** 1 (left), 2 (right)
- **Recording environment:** Wat (underwater), Air (in air)
- **Recording sensitivity:** sensitivity for the entire system (dBV/pa)
 - If the sensitivity is unclear, please use 0 to measure the relative change
- **Reading interval:** duration of each recording clip in the duty cycle (second)
 - If a recording clip is too big (hours...), then you can try 60 second or 300 second.
- **Time resolution:** the desired time resolution of a long-term spectrogram (second)
 - No longer than the reading interval
- **FFT size:** number of samples in the spectral analysis
 - Frequency resolution will be: sampling frequency/FFT size
- **Upper and lower frequency limits:** the desired frequency range of a long-term spectrogram (Hz)
- **Output file name**

Check the time stamps

- The program will get the beginning time of each recording clip from the file name
 - Make sure all the recordings in the same folder have the same format of time stamp
- Please choose the appropriate position of the following date format on the file name :
 - **Year, Month, Day, Hour, Minute, Second**
 - Position of the first digit
 - Position of the final digit
 - **Extra labels before input year**
 - If the year stamp is not complete, e.g., 2018 → 18, then put “20” here

1207984160.180528171502.wav

1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27

Year	<input type="text" value="12"/>	<input type="text" value="13"/>
Month	<input type="text" value="14"/>	<input type="text" value="15"/>
Day	<input type="text" value="16"/>	<input type="text" value="17"/>
Hour	<input type="text" value="18"/>	<input type="text" value="19"/>
Minute	<input type="text" value="20"/>	<input type="text" value="21"/>
Second	<input type="text" value="22"/>	<input type="text" value="23"/>
Extra labels before input year	<input type="text" value="20"/>	

Run analysis

- Press the button of “**Run analysis**”, then the program will process the entire folder and display the current progress
- Once the analysis has been done, three types of long-term spectrogram will be displayed
 - **Median-based long-term spectrogram**
 - **Mean-based long-term spectrogram**
 - **Difference-based long-term spectrogram**
- A **mat file** which contains all the results and meta-data will be saved in the folder of LTSA_gui.exe

